

Lecture (07)


STP (II)


By:

Dr. Ahmed ElShafee

Dr. Ahmed ElShafee, ACU : Spring 2016, Practical App.
Networks I

- Such design creates a single point of failure. We could easily tweak this simple design to make it more resilient by adding an extra path between **SW2** and **SW3**





```

SW2
+++
enable
config t
interface fa0/22
switchport mode trunk
end
copy running-config startup-config

```

```

SW03
++++
enable
config t
interface fa0/22
switchport mode trunk
end
copy running-config startup-config

```

-
- The redundant connection between **SW2** and **SW3** creates a loop.
 - The loop in turn, will create three serious problems.
 - **Duplicate Frame Delivery**
 - **MAC Address Table Instability**
 - **Broadcast Storm**
 - The last one in the list will eventually render our system unavailable.

◦ Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I

STP

- Spanning-Tree Protocol (turned on by default), which will dynamically block redundant connections creating a loop free topology.
- Should the primary link fail, the one that is in the blocking state will start forwarding the traffic in about 30 seconds by default

Spanning-Tree Protocol Overview

STP is a layer 2 loop prevention mechanism.

- Switches running this protocol use special frames called **Bridge Protocol Data Unit (BPDU)**.
- STP let switches create a loop free topology. This is accomplished using three distinct phases:
 1. Select **a single switch** to be the **root bridge** machine which is the central device in the layer 2 network.
 - This machine will have all its ports in the forwarding state (**designated port role**).
 2. All other switches (non-root switches), will select **a single path** towards the root bridge.


Y

Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I


-
- That port is called the '**root port**' and will be forwarding traffic that is destined out of the switch through the root bridge.
 - This path is the least cost (best) path towards the root.
 - 3. All other switches will select **a single path per segment** in order to block stop the loop.
 - The port that is forwarding traffic is called **designated port**.
 - The port that is blocking traffic to stop the loop is called **non-designated port**.

A

Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I



- administrator should configure the root bridge.
- Typically, the most powerful switch in the center of the network plays that role.
- You do not want some access switch to be transmitting the frames between other switches.
- Access switches are designed to connect your computers to the network, and not to handle the majority of the traffic between the switches which root bridge must deal with.
- If you do not configure root bridge yourself, the switch with the lowest MAC address becomes the root since the priority is identical on all of them by default.




Discovering root switch

```
sw01#show spanning-tree vlan 1
VLAN0001
  Spanning tree enabled protocol ieee
  Root ID  Priority  32769
            Address  000D.BD98.4239
            Cost       19
            Port      24(FastEthernet0/24)
            Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec
```

```
Bridge ID  Priority  32769 (priority 32768 sys-id-ext 1)
          Address  00D0.9721.49E8
          Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec
          Aging Time 20
```

Interface	Role	Sts	Cost	Prio.Nbr	Type
Fa0/24	Root	FWD	19	128.24	P2p
Fa0/23	Desg	FWD	19	128.23	P2p



SW02#show spanning-tree vlan 1

VLAN0001


Spanning tree enabled protocol ieee
Root ID Priority 32769
Address 000D.BD98.4239
This bridge is the root
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 32769 (priority 32768 sys-id-ext 1)

Address 000D.BD98.4239
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
Aging Time 20

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----------	------	-----	------	----------	------

Fa0/24	Desg	FWD	19	128.24	P2p
Fa0/22	Desg	FWD	19	128.22	P2p



sw03#show spanning-tree vlan 1

VLAN0001

Spanning tree enabled protocol ieee
Root ID Priority 32769
Address 000D.BD98.4239
Cost 19
Port 22(FastEthernet0/22)
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 32769 (priority 32768 sys-id-ext 1)


Address 00E0.A303.8D77
Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec
Aging Time 20

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----------	------	-----	------	----------	------

Fa0/22	Root	FWD	19	128.22	P2p
Fa0/23	Altn	BLK	19	128.23	P2p

Setting root switch, Method 1

- decrement the priority on **SW1** and leave the default value on the other switches, The lowest priority value allowed is zero and if higher needs to be used, it must be an increment of 4096.



FL01-R03-SW03#show vlan

VLAN Name	Status	Ports
1 default	active	Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/21, Fa0/24
2 Finance	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5
3 HR	active	Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10
4 Administration	active	Fa0/11, Fa0/12, Fa0/13, Fa0/14 Fa0/15

FL01-R03-SW03(config)#spanning-tree vlan 1,2,3,4 priority 0

FL01-R03-SW03(config)#end

FL01-R03-SW03#copy running-config startup-config

sw01#show spanning-tree vlan 1

VLAN0001

Spanning tree enabled protocol ieee

Root ID Priority 1

Address 00D0.9721.49E8

This bridge is the root

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 1 (priority 0 sys-id-ext 1)

Address 00D0.9721.49E8

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 20

Interface Role Sts Cost Prio.Nbr Type

Fa0/23 Desg FWD 19 128.23 P2p

Fa0/24 Desg FWD 19 128.24 P2p

```
SW02#show spanning-tree vlan 1
```

VLAN0001

Spanning tree enabled protocol ieee

Root ID Priority 1

Address 00D0.9721.49E8

Cost 19

Port 24(FastEthernet0/24)

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 32769 (priority 32768 sys-id-ext 1)

Address 000D.BD98.4239

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 20

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----------	------	-----	------	----------	------

Fa0/24	Root	FWD	19	128.24	P2p
--------	------	-----	----	--------	-----

Fa0/22	Desg	FWD	19	128.22	P2p
--------	------	-----	----	--------	-----

```
sw03#show spanning-tree vlan 1
```

VLAN0001

Spanning tree enabled protocol ieee

Root ID Priority 1

Address 00D0.9721.49E8

Cost 19

Port 23(FastEthernet0/23)

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 32769 (priority 32768 sys-id-ext 1)

Address 00E0.A303.8D77

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 20

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----------	------	-----	------	----------	------

Fa0/23	Root	FWD	19	128.23	P2p
--------	------	-----	----	--------	-----

Fa0/22	Altn	BLK	19	128.22	P2p
--------	------	-----	----	--------	-----

Setting root switch, Method 2

- Use spanning-tree vlan root primary macro command which decrements the priority value using Cisco best practices.

FL01-R03-SW03#show vlan

VLAN Name	Status	Ports
1 default	active	Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/21, Fa0/24
2 Finance	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5
3 HR	active	Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10
4 Administration	active	Fa0/11, Fa0/12, Fa0/13, Fa0/14 Fa0/15

FL01-R03-SW03(config)#spanning-tree vlan 1,2,3,4 root primary

FL01-R03-SW03(config)#end

FL01-R03-SW03#copy running-config startup-config

sw01#show spanning-tree vlan 1

VLAN0001

Spanning tree enabled protocol ieee

Root ID Priority 24577

Address 00D0.9721.49E8

This bridge is the root

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 24577 (priority 24576 sys-id-ext 1)

Address 00D0.9721.49E8

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 20

Interface Role Sts Cost Prio.Nbr Type

Fa0/24	Desg	FWD	19	128.24	P2p
Fa0/23	Desg	FWD	19	128.23	P2p

```

SW02#show spanning-tree vlan 1
VLAN0001
  Spanning tree enabled protocol ieee
  Root ID  Priority  24577
    Address  00D0.9721.49E8
    Cost     19
    Port     24(FastEthernet0/24)
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec

  Bridge ID Priority  32769 (priority 32768 sys-id-ext 1)
    Address  000D.BD98.4239
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec
    Aging Time 20

Interface      Role Sts Cost      Prio.Nbr Type
-----
Fa0/22        Desg FWD 19       128.22  P2p
Fa0/24        Root FWD 19      128.24  P2p

```

٢١

Dr. Ahmed ElShafee, ACU : Spring 2016, Practical App. Networks I

```

sw03#show spanning-tree vlan 1
VLAN0001
  Spanning tree enabled protocol ieee
  Root ID  Priority  24577
    Address  00D0.9721.49E8
    Cost     19
    Port     23(FastEthernet0/23)
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec

  Bridge ID Priority  32769 (priority 32768 sys-id-ext 1)
    Address  00E0.A303.8D77
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec
    Aging Time 20

Interface      Role Sts Cost      Prio.Nbr Type
-----
Fa0/22        Altn BLK 19      128.22  P2p
Fa0/23        Root FWD 19      128.23  P2p


```

٢٢

Dr. Ahmed ElShafee, ACU : Spring 2016, Practical App. Networks I

Add redundant root ports

- Firstly lets add redundant connection between SW 1,2
- Collect spanning-tree information on vlan 1 of both SW01, SW02




٢٤

Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I

```
SW01
++++
enable
config t
interface fa0/21
switchport mode trunk
end
copy running-config startup-config
```

```
SW02
++++
enable
config t
interface fa0/21
switchport mode trunk
end
copy running-config startup-config
```




٢٥

Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I

```

sw01#show spanning-tree vlan 1
VLAN0001
  Spanning tree enabled protocol ieee
  Root ID  Priority  24577
    Address  00D0.9721.49E8
    This bridge is the root
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec

```



```

  Bridge ID  Priority  24577 (priority 24576 sys-id-ext 1)
    Address  00D0.9721.49E8
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec
    Aging Time 20


```

Interface	Role	Sts	Cost	Prio.Nbr	Type
Fa0/21	Desg	FWD	19	128.21	P2p
Fa0/23	Desg	FWD	19	128.23	P2p
Fa0/24	Desg	FWD	19	128.24	P2p

```

SW02#show spanning-tree vlan 1
VLAN0001
  Spanning tree enabled protocol ieee
  Root ID  Priority  24577
    Address  00D0.9721.49E8
    Cost      19
    Port      21(FastEthernet0/21)
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec

```



```

  Bridge ID  Priority  32769 (priority 32768 sys-id-ext 1)
    Address  000D.BD98.4239
    Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec
    Aging Time 20

```

Interface	Role	Sts	Cost	Prio.Nbr	Type
Fa0/22	Desg	FWD	19	128.22	P2p
Fa0/24	Altn	BLK	19	128.24	P2p
Fa0/21	Root	FWD	19	128.21	P2p

Swap alternative and root ports in SW02 (24, 21)

- @ root switch (SW1) decrease priority of alternative port (24) to 64

```
en
config t
interface fa0/24
spanning-tree vlan 1 port-priority 64
end
copy running-config startup-config
```

٢٤

Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I

```
sw01#show spanning-tree vlan 1
VLAN0001
  Spanning tree enabled protocol ieee
  Root ID  Priority  24577
            Address  00D0.9721.49E8
            This bridge is the root
            Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec

  Bridge ID  Priority  24577 (priority 24576 sys-id-ext 1)
            Address  00D0.9721.49E8
            Hello Time 2 sec  Max Age 20 sec  Forward Delay 15 sec
            Aging Time 20

  Interface      Role Sts Cost      Prio.Nbr Type
  -----
  Fa0/21        Desg FWD 19      128.21  P2p
  Fa0/23        Desg FWD 19      128.23  P2p
  Fa0/24        Desg FWD 19      64.24   P2p
```

٢٥

Dr. Ahmed ElShafee, ACU : Spring 2016, Practical App. Networks I

```
SW02#show spanning-tree vlan 1
```

VLAN0001

Spanning tree enabled protocol ieee

Root ID Priority 24577

Address 00D0.9721.49E8

Cost 19

Port 24(FastEthernet0/24)

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Bridge ID Priority 32769 (priority 32768 sys-id-ext 1)

Address 000D.BD98.4239

Hello Time 2 sec Max Age 20 sec Forward Delay 15 sec

Aging Time 20

Interface	Role	Sts	Cost	Prio.Nbr	Type
-----------	------	-----	------	----------	------

Fa0/22	Desg	FWD	19	128.22	P2p
--------	------	-----	----	--------	-----

Fa0/24	Root	FWD	19	128.24	P2p
--------	------	-----	----	--------	-----

Fa0/21	Altn	BLK	19	128.21	P2p
--------	------	-----	----	--------	-----

Load balancing between redundant ports

- @ root switch (SW01), Check spanning tree on shared ports

```
sw01#show spanning-tree interface FastEthernet 0/21
```

Vlan	Role	Sts	Cost	Prio.Nbr	Type
------	------	-----	------	----------	------

VLAN0001	Desg	FWD	19	128.21	P2p
----------	------	-----	----	--------	-----

VLAN0002	Desg	FWD	19	128.21	P2p
----------	------	-----	----	--------	-----

VLAN0003	Desg	FWD	19	128.21	P2p
----------	------	-----	----	--------	-----

VLAN0004	Desg	FWD	19	128.21	P2p
----------	------	-----	----	--------	-----

```
sw01#show spanning-tree interface FastEthernet 0/24
```

Vlan	Role	Sts	Cost	Prio.Nbr	Type
------	------	-----	------	----------	------

VLAN0001	Desg	FWD	19	128.24	P2p
----------	------	-----	----	--------	-----

VLAN0002	Desg	FWD	19	128.24	P2p
----------	------	-----	----	--------	-----

VLAN0003	Desg	FWD	19	128.24	P2p
----------	------	-----	----	--------	-----

VLAN0004	Desg	FWD	19	128.24	P2p
----------	------	-----	----	--------	-----

- @ SW02, Check spanning tree on shared ports

SW02>en

SW02#show spanning-tree interface FastEthernet 0/21

Vlan	Role	Sts	Cost	Prio.Nbr	Type
------	------	-----	------	----------	------

VLAN0001	Root	FWD	19	128.21	P2p
VLAN0002	Root	FWD	19	128.21	P2p
VLAN0003	Root	FWD	19	128.21	P2p
VLAN0004	Root	FWD	19	128.21	P2p

SW02#show spanning-tree interface fa0/24

Vlan	Role	Sts	Cost	Prio.Nbr	Type
------	------	-----	------	----------	------

VLAN0001	Altn	BLK	19	128.24	P2p
VLAN0002	Altn	BLK	19	128.24	P2p
VLAN0003	Altn	BLK	19	128.24	P2p
VLAN0004	Altn	BLK	19	128.24	P2p

٣١

Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I

- @ root switch (SW01) decrease vlan3,4 priorities

interface FastEthernet 0/24

spanning-tree vlan 3 port-priority 64


spanning-tree vlan 4 port-priority 64

- Check spanning tree on SW02 shared ports

SW02#show spanning-tree interface FastEthernet 0/21

Vlan	Role	Sts	Cost	Prio.Nbr	Type
------	------	-----	------	----------	------

VLAN0001	Root	FWD	19	128.21	P2p
VLAN0002	Root	FWD	19	128.21	P2p
VLAN0003	Altn	BLK	19	128.21	P2p
VLAN0004	Altn	BLK	19	128.21	P2p




٣٢

Dr. Ahmed ElShafee, ACU Spring 2016, Practical Applications in Computer Networks I

```
SW02#show spanning-tree interface FastEthernet 0/24
```

Vlan	Role	Sts	Cost	Prio.	Nbr	Type
------	------	-----	------	-------	-----	------

VLAN0001	Altn	BLK	19	128.24	P2p
VLAN0002	Altn	BLK	19	128.24	P2p
VLAN0003	Root	FWD	19	128.24	P2p
VLAN0004	Root	FWD	19	128.24	P2p



٢٢

Dr. Ahmed ElShafee, ACU Spring :

```
sw01#show spanning-tree interface FastEthernet 0/21
```

Vlan	Role	Sts	Cost	Prio.	Nbr	Type
------	------	-----	------	-------	-----	------

VLAN0001	Desg	FWD	19	128.21	P2p
VLAN0002	Desg	FWD	19	128.21	P2p
VLAN0003	Desg	FWD	19	128.21	P2p
VLAN0004	Desg	FWD	19	128.21	P2p

```
sw01#show spanning-tree interface FastEthernet 0/24
```

Vlan	Role	Sts	Cost	Prio.	Nbr	Type
------	------	-----	------	-------	-----	------

VLAN0001	Desg	FWD	19	128.24	P2p
VLAN0002	Desg	FWD	19	128.24	P2p
VLAN0003	Desg	FWD	19	64.24	P2p
VLAN0004	Desg	FWD	19	64.24	P2p

٣٤

Dr. Ahmed ElShafee, ACU : Spring 2016, Practical App. Networks I



Thanks,..

See you next week (ISA),...



Dr. Ahmed ElShafee, ACU : Spring 2016, Practical App.
Networks I